



Options – Time response: Default Settings for older RoeTests:



Currently I use the following settings for the RoeTest V5-V7:



Currently I use the following settings for the RoeTest V8:

RoeTest - professional tube-testing-system - time behaviour

operation:	delay time in ms
Switching relays by computer	100
Switching relays by RoeTest (current ranges)	200
Delay in data transmission (interface)	3
short delay:	100
medium delay:	500
long delay:	1000
Delay between curve traces	250
Delay between curve traces of neon stabilizer	1000

Used at various places in this software

Time behaviour: delays can be adjusted so software works properly

default values abort OK